

pfSense - Bug #9258

error when deleting P2

01/07/2019 01:16 AM - Idar Lund

Status:	Resolved	Start date:	01/07/2019
Priority:	Low	Due date:	
Assignee:	Jim Pingle	% Done:	100%
Category:	IPsec	Estimated time:	0.00 hour
Target version:	2.5.0	Affected Architecture:	
Affected Version:	2.4.4_1		

Description

When trying to delete a (tunnel mode) phase 2 entry were both "tunnel" and "vti" modes are mixed the GUI is responding with an error:
The following input errors were detected:
Cannot delete a VTI Phase 2 while the interface is assigned. Remove the interface assignment before deleting this P2.
Please see attached screenshot

Workaround:

1. Remove the vti interface
2. remove all p2
3. recreate vti p2
4. readd vti interface

Associated revisions

Revision 37c60830 - 08/27/2019 10:16 AM - Jim Pingle

Only prevent deleting IPsec VTI P2 when set to VTI. Fixes #9258

Revision 0caa971e - 08/27/2019 10:17 AM - Jim Pingle

Only prevent deleting IPsec VTI P2 when set to VTI. Fixes #9258

(cherry picked from commit 37c6083084617e3fd079876352109ff38aa6613b)

History

#1 - 01/07/2019 01:19 AM - Idar Lund

Edit:

Workaround:

1. disable vti interface
2. remove all unwanted p2
3. enable vti interface

#2 - 08/13/2019 10:45 AM - Mix Room

Problem remains on 2.4.4-RELEASE-p3
Work-around works.

#3 - 08/13/2019 10:51 AM - Jim Pingle

- Assignee set to Jim Pingle
- Target version set to 2.5.0

#4 - 08/27/2019 10:25 AM - Jim Pingle

- Status changed from New to Feedback

- % Done changed from 0 to 100

Applied in changeset [37c6083084617e3fd079876352109ff38aa6613b](#).

#5 - 10/12/2019 02:36 AM - Viktor Gurov

Jim Pingle wrote:

Applied in changeset [37c6083084617e3fd079876352109ff38aa6613b](#).

Tested on 2.5.0.a.20191011.1853

P2 tunnel mode is now removed correctly

Resolved

#6 - 10/12/2019 08:31 AM - Jim Pingle

- Status changed from Feedback to Resolved

Files

Screenshot 2019-01-07 at 08.08.19.png	258 KB	01/07/2019	Idar Lund
---------------------------------------	--------	------------	-----------